





How to Create and Transfer Bullet Files with Kestrel LiNK Ballistics App




Note: This guide assumes you can already connect with the KLB app, if not, please see [this guidance](#) first.




1) Connect to the Kestrel LiNK Ballistics app and select **Gun Profile Management**.




2) Click ellipsis or + sign at the top to create a new profile.



3) Select Bullet Library to view library of bullets available.




4) Choose Bullet Manufacturer.




5) Choose bullet size and weight.




How to Create and Transfer Bullet Files with Kestrel LiNK Ballistics App




6) Select Solver type.
Note: 4DOF is not available for all the bullets in library, but would be best option if available.



7) Enter a name and pertinent gun information and click ellipsis to save profile.



8) You must click the radio button next to all profiles you want to send. For iOS, there is a Select button to make radio buttons appear.



9) When all profiles being sent are selected (3 at most), select Send Profiles to send them to a Kestrel. You will have an option to overwrite or append profiles on Kestrel. Get will retrieve all profiles on the Kestrel.